

Connect to your business network, from home, to access your files and applications.

To be able to connect from home, we provide you with a management account as well as passwords that your employees can use to access your business network from their computers at home. You can aply for up to 10 accounts per network.

The facility is provided to customers who have their business network connected with Cyta's VPN networking products, either DSL Business or Ethernet access.

It is also provided to customers who have their business network connected with Internet Business or Dedicated Intrenet products over Ethernet, however at least one connection is needed with Cyta's VPN networking products.

Instructions for setting up and using a home VPN connection.

(Windows 10)

1. CONNECTION SETUP

On the screen Windows Settings > VPN :

Click on 'Add a VPN connection'



Γ	Settings					
	ŝ	Home	VPN			
	Fir Netv	nd a setting $ ho$ work & Internet	+ Add a VPN connection			
	₽	Status	Advanced Options			
	臣	Ethernet	Allow VPN over metered networks			
	ß	Dial-up	Allow VPN while roaming			
	ത്ര	VPN	On On			
	Ċ	Data usage	Related settings			
	⊕	Proxy	Change adapter options			
			Change advanced sharing options			
			Network and Sharing Center			
			Windows Firewall			

On the screen VPN enter the following settings:

VPN Provider : Windows (built-in)

Connection Name : Cyta VPN

Server name or address : 195.14.129.98

VPN type : Point to point tunneling protocol (PPTP)

User name : < enter the username that Cyta gave you >

Password : < enter the password that Cyta gave you >



Click : Remember my sign-in info Click : Save

Settings			_	×
Add a VPN connection				
VDN provider				
Windows (built-in)	~			
Connection name				
Cyta VPN				
Server name or address				
195.14.129.98				
VPN type				
Point to Point Tunneling Protocol (PPTP)	\sim			
Type of sign-in info				
User name and password	\sim			
User name (optional)				
Password (optional)				
		Save	Cancel	

2. USING THE CONNECTION

On the screen Windows Settings > Click 'Connect' on the icon 'Cyta VPN'



Settings			
🔅 Home	VPN		
Find a setting	+ Add a VPN connection		
Def Status	Cyta VPN		
記 Ethernet	Connect Advanced options Remove		
ଳ Dial-up	Advanced Ontions		
% VPN	Allow VPN over metered networks		
🕒 Data usage	On On		
Proxy	Allow VPN while roaming On		
	Related settings		
	Change adapter options		
	Change advanced sharing options		
	Network and Sharing Center		
	Windows Firewall		

Note :

When the computer connects to the VPN it gets an IP address in the range 192.168.0.1/24 and can connect to any point within the corporate VPN.